Overview

Firmware update tool is an application used to update monitor firmware.

Firmware Update Pre-requisites

1 The monitor must be connected to a power source during the firmware updating process.



2 Make sure there is only ONE video input source, e.g. DisplayPort, HDMI, or USB Type-C, from the computer to the monitor.

NOTE: Ensure that all other video cables between the monitor and the computer are unplugged.

3 Connect the USB Type-C cable or USB Type-C cable directly between the monitor and your computer. Do not use any other device between this connection.



NOTE: Ensure that other USB cables and USB devices between the monitor and the computer are unplugged.



NOTE: Disconnect all other monitors from the notebook or desktop. This will ensure that only one display is connected while conducting firmware update.

NOTE: It is recommended to update the firmware with a notebook as the monitor screen may go blank during the firmware update process.



4 Exit DDM (Dell Display Manager) application before conducting firmware update.





NOTE: Please disable sleep mode before you launch the firmware update.



Updating firmware

- 1 Double-click the ISP icon 🔜.
- 2 Initializing for device status.



3 The utility will load the firmware file automatically. Or, you can select your file manually by clicking ... and navigating to the UPG firmware file.

Monitor Firmw	vare Update Utility			
File Path	C-\D_II\Gamma\D242.0\ID4220\D242.0\ID		_	
Model No	C:\Dell\firmware\P3424WE\M2B102\P3424WE_M2B102 P3424WE	2.0PG		
Current Firmware	M2B101			
New Firmware	M2B102			
File Checksum	716B			
 Update takes up to 12 minu 	tes. Do not power off or disconnect cable while updating.			
			Update	

4 Click **Update**. The utility will start updating the new firmware.

File Path	C:\Dell\firmware\P3424WE\M2B102\P3424WE_M2B102.UPG
Model No	P3424WE
Current Firmware	M2B101
New Firmware	M2B102
File Checksum	716B
Updating .	
1 Update takes up to 12 min	utes. Do not power off or disconnect cable while updating.

5 Once the updating process is completed, please follow the on-screen instructions to restart your monitor.

File Path	C:\Dell\firmware\P3424WE\M2B102\P3424WE_M2B102.U	UPG		
Model No	P3424WE			
Current Firmware	M2B101			
New Firmware	M2B102			
File Checksum	716B			
Update Successful To complete update, turn of and restart the monitor.	f the monitor and unplug both the USB and power cables, then replug the power c	able		
			Close	



NOTE: Update takes up to 12 minutes. Do not power off or disconnect cable while updating.



Troubleshooting

Errors	Possible Solutions	
File permission error	 Try saving the firmware file in another location. Check if the firmware file has read permission. Check if you have owner rights for the firmware file. Or, run this utility with administrator privileges. 	
Monitor not detected	 Follow Firmware Update Pre-requisites to check if the power and USB cables are properly connected to your computer and reopen the Monitor Firmware Update Utility. In USB of the OSD menu, make sure the USB port is set to the corresponding input signal. 	
Write protection error	Re-try updating with the following steps:	
Flash erase error	[–] 1 Close the Monitor Firmware Update Utility.	
Update error	 2 Turn off the monitor by pressing the power button. 2 De plug the power cord 	
Monitor firmware checksum error	 3 Re-plug the power cord. 4 Turn on the monitor. 5 Try updating again with the Monitor Firmware Update Utility. 	
USB device inactive after new firmware installation.	Re-try the updating steps from 1 to 4 as stated above.	
A warning message appears: "Firmware update was not completed. Please update the monitor firmware again."	Re-try updating the monitor's firmware. Do not turn off the ISP tool until the update is complete.	